

BALANCE

UV GEL SYSTEM

Balance Sculpting Kit Instructions

For Professional Use Only



Balance UV Gel System allows the nail tech unsurpassed control in perfect color options. The Balance System offers durability, adhesion, flexibility and strength

Natural Nail Prep

Proper preparation of the natural nail and workstation are preventative steps to guard against problems and will help you get the best possible results from your professional nail service.

1. Spray your hands and clients hands with Sanitize and gently massage. Sanitize will help reduce the spread of infection.
2. Apply a very small dollop of NSI 's Vanish Cuticle Dissolve to each cuticle and gently massage. Gently push back the eponychium, and remove any non-living tissue. Wipe excess Vanish from each nail, using a Nail Wipe moistened with NSI Cleanse.
3. Remove the shine from the natural nail using NSI Prep 180 grit file following the contour of the nail and moving the file in the direction of nail plate growth.
4. Remove excess dust with the NSI Plush Brush.
5. Using an NSI Nail Wipe saturated with Nail Pure Plus, press and rub into natural nail, sidewalls, and under free edge to remove oil, moisture, and contaminants. Allow natural nail to become chalky white.
6. If extensions are desired, adhere tip or fit form at this time.
7. Apply Balance Bond (Acid-Free) Primer liberally to the natural nail. Remove the brush from the bottle and wipe along the edge of the bottle, then brush onto two natural nails. Re-dip the brush and repeat the process until the nails are coated. Allow to dry for one minute. They will not appear chalky white.

Balance Sculpting Gels on a Form or Tip

Note: When using Radiant White Sculptor Gel, it is recommended to use Elation Clear Tips or Balance Clear UV Gel Forms. For best results, cure for 2 minutes or 120 seconds in an Ultra Pro Full Hand UV Lamp.

1. Follow directions for Natural Nail Prep
2. Apply an Elation Clear Tip, cut, file and blend, or Balance Clear UV Gel Form.
3. Apply Balance Bond according to the instructions in Natural Nail Prep.

Zone 1: Smile line and extension edge

1. Using the flattened side of a #5 or #7 Touch Tip Brush, scoop into the container and gather a medium to large amount of gel. Rotate the container and the brush; keep the gel on the tip or flags of the brush.

Note: For veteran gel users, the sculpting gels are designed to stay where you put them, so you can sculpt all 5 nails without the need to "freeze" or "lock".

Note: For beginner gel users, it is recommended to begin with the thumb and "freeze" or "lock" each zone 1, smile line and extension edge, for 10 seconds. Then, cure all 5 nails at one time for 120 seconds (2 minutes.)

2. Place the gel near the natural free edge line. Twirl the brush to release and slightly warm the gel. Do not overwork.
3. With a light feathery touch, start creating the smile line.
4. Pull, glide, float and stretch the gel to pull over tip or form to create extension.
5. Use a light "floating" touch and keep your brush handle angled downward.
6. Wipe any gel residue from brush on a clean lint-free NSI Nail Wipe.
7. Back brush smile line to make a smooth crisp line, if necessary.
8. Freeze in an Ultra Pro Full Hand UV Lamp for 10 seconds.

9. Repeat process on nails of one hand until all zone 1, smile lines and extension edges, have been created and "frozen".
10. Cure the nails of one hand in an Ultra Pro Full Hand UV Lamp for 120 seconds (2 minutes).

Zones 2 and 3

1. Using the flattened side of a #5 or #7 Touch Tip Brush, gather a medium amount of Balance Builder Gel. Customize with your choice of 4 color options.
2. Starting in zone 3, and keeping the brush parallel to the nail, stretch and pull the gel over the entire length of the nail using a light "floating" touch to create a thin "lock-in" base layer.

Note: If the first layer too thick it could prevent proper adhesion.

Note: When using Builder Radiant Pink, be careful to use only in zone 2 and 3, and not to drag or brush over the white of the extension edge.

3. Check the nail from all angles to ensure proper apex placement. Add a small amount of gel to the upper arch, if necessary.
4. Cure in NSI Ultra Professional Full Hand Lamp for 90 seconds.
5. Apply a second coat of Builder Gel, if necessary.
6. Wipe off tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
7. File, shape and refine nails.
8. Remove excess dust with NSI Plush Brush.
9. Use an NSI Nail Wipe lightly saturated with NSI Cleanse to remove any dust that may be hiding in sidewalls.
10. Using the flattened side of the Touch Tip brush of your choice, apply a medium amount of Finish Clear to the entire surface making sure to seal and cap all edges.
11. Cure for 90 seconds.
12. Remove tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
13. Condition surrounding skin with Nuture Oil.

All NSI products are developed and manufactured by NSI and are designed for professional use only.

All NSI products must be kept at room temperature (65°-80°F)

WARNING:

Professional use only. May cause irritation of skin and eyes. In case of eye contact, flush with water. If skin irritation occurs, discontinue use. In case of emergency, retain product packaging and contact a physician or Infotrac Chemical Emergency Response at 1-800-535-5053 or 1-352-323-3500 immediately. UV curable - Keep out of direct sunlight.

Made in USA by NSI
W. Conshohocken, PA 19428
Tel: 800.354.6741 • 610.825.1524 • Fax: 610.825.2738

www.nsinails.com

NARITAWEG 165, 1043 BW AMSTERDAM, NL